

The pdfscape package

Heiko Oberdiek*

<heiko.oberdiek at gmail.com>

2016/05/14 v0.11

Abstract

Package `pdfscape` adds PDF support to the environment landscape of package `lscape` by setting the PDF page attribute `/Rotate`.

Contents

1	Documentation	2
1.1	Supported drivers	2
1.2	Caveat	2
1.3	Requirements	2
1.4	Usage	2
2	Implementation	2
2.1	Package identification	2
2.2	Driver options	2
2.3	Autodetection of driver	3
2.3.1	Driver <code>pdftex</code>	3
2.3.2	Driver <code>xetex</code>	3
2.3.3	Detect driver based on <code>\Gin@driver</code>	4
2.3.4	Driver <code>dvips</code>	4
2.4	Driver implementation	4
2.4.1	<code>pdfTeX</code>	5
2.4.2	PostScript driver	5
2.4.3	Driver <code>dvipdfm</code>	6
2.5	Driver independent stuff	6
3	Test	7
3.1	Driver detection tests	7
3.2	Test for <code>\PLS@CheckAngle</code>	8
3.3	Test for rotate	8
4	Installation	10
4.1	Download	10
4.2	Bundle installation	10
4.3	Package installation	10
4.4	Refresh file name databases	11
4.5	Some details for the interested	11
5	Catalogue	11

*Please report any issues at <https://github.com/ho-tex/oberdiek/issues>

6 History	12
[2001/01/15 v0.1]	12
[2001/02/04 v0.2]	12
[2004/05/11 v0.3]	12
[2004/05/12 v0.4]	12
[2006/02/20 v0.5]	12
[2006/04/24 v0.6]	12
[2007/04/11 v0.7]	13
[2007/04/17 v0.8]	13
[2007/10/21 v0.9]	13
[2008/08/11 v0.10]	13
[2016/05/14 v0.11]	13

1 Documentation

1.1 Supported drivers

- pdftex,luatex
- dvips, dvipsone, pctx32, pctxps (and other drivers that provide a non-empty `\Gin@PS@raw`)
- dvipdfm

1.2 Caveat

Depending on the configuration Ghostscript adds a guessed rotation entry by its own. This can lead to two `/Rotate` entries per page. To prevent this behaviour set the parameter `AutoRotatePages` to `/None`, eg:

```
ps2pdf -dAutoRotatePages=/None
```

1.3 Requirements

- The package `lscape`.
- The package `atbegshi` for all drivers except `pdftex,luatex`.

1.4 Usage

Load this package instead of or after package `lscape`:

```
\usepackage{pdfscape}
\begin{landscape}...\end{landscape}
```

2 Implementation

2.1 Package identification

```
1 (*package)
```

Package identification.

```
2 \NeedsTeXFormat{LaTeX2e}
3 \ProvidesPackage{pdfscape}%
4 [2016/05/14 v0.11 Display of landscape pages in PDF (HO)]
```

2.2 Driver options

```
5 \let\PLS@option\@empty
6 \let\PLS@driver\@empty
7 \def\PLS@temp#1#2{%
```

```

8 \DeclareOption{#1}{%
9 \let\PLS@option\CurrentOption
10 \def\PLS@driver{#2}%
11 }%
12 }
13 \PLS@temp{pdftex}{pdftex}
14 \PLS@temp{luatex}{pdftex}
15 \PLS@temp{dvips}{dvips}
16 \PLS@temp{dvipsone}{dvips}
17 \PLS@temp{pctexps}{dvips}
18 \PLS@temp{dvipdfm}{dvipdfm}
19 \PLS@temp{dvipdfmx}{dvipdfm}
20 \PLS@temp{xetex}{dvipdfm}
21 \let\PLS@temp\@empty
22 \DeclareOption*{%
23 \ifx\PLS@temp\@empty
24 \let\PLS@temp\CurrentOption
25 \else
26 \edef\PLS@temp{\PLS@temp,\CurrentOption}%
27 \fi
28 }
29 \ProcessOptions*
30 \ifx\PLS@option\@empty
31 \else
32 \expandafter\PassOptionsToPackage\expandafter{\PLS@option}{lscape}%
33 \fi
34 \ifx\PLS@temp\@empty
35 \else
36 \expandafter\PassOptionsToPackage\expandafter{\PLS@temp}{lscape}%
37 \fi
38 \RequirePackage{lscape}

```

2.3 Autodetection of driver

2.3.1 Driver pdftex

```

39 \RequirePackage{ifpdf}[2006/02/20]
40 \def\PLS@temp{pdftex}
41 \ifpdf
42 \ifx\PLS@driver\@empty
43 \let\PLS@driver\PLS@temp
44 \PackageInfo{pdfscape}{Auto-detected driver: \PLS@temp}%
45 \fi
46 \ifx\PLS@driver\PLS@temp
47 \else
48 \PackageError{pdfscape}{%
49 The driver option '\PLS@option' is not compatible\MessageBreak
50 with pdfTeX in PDF mode, using driver 'pdftex' instead%
51 }\@ehc
52 \let\PLS@driver\PLS@temp
53 \fi
54 \fi

```

2.3.2 Driver xetex

```

55 \RequirePackage{ifxetex}%
56 \def\PLS@temp{dvipdfm}
57 \ifxetex
58 \ifx\PLS@driver\@empty
59 \let\PLS@driver\PLS@temp
60 \PackageInfo{pdfscape}{%
61 Auto-detected driver: \PLS@temp\space(xetex)%
62 }%
63 \fi
64 \ifx\PLS@driver\PLS@temp

```

```

65 \else
66 \PackageError{pdfscape}{%
67   The driver option '\PLS@option' is not compatible\MessageBreak
68   with XeTeX, using driver for XeTeX (dvipdfm) instead%
69 } \@ehc
70 \let\PLS@driver\PLS@temp
71 \fi
72 \fi

```

2.3.3 Detect driver based on \Gin@driver

```

73 \def\PLS@temp#1#2{%
74 \ifx\PLS@driver\@empty
75 \begingroup
76 \def\PLS@temp{#1.def}%
77 \expandafter\endgroup
78 \ifx\PLS@temp\Gin@driver
79 \def\PLS@driver{#2}%
80 \PackageInfo{pdfscape}{%
81   Auto-detected driver: \PLS@driver\space(#1)%
82 }%
83 \fi
84 \fi
85 }
86 \PLS@temp{dvipdfm}{dvipdfm}
87 \PLS@temp{dvipdfmx}{dvipdfm}
88 \PLS@temp{dvips}{dvips}
89 \PLS@temp{dvipsone}{dvips}
90 \PLS@temp{pctexps}{dvips}

```

2.3.4 Driver dvips

```

91 \ifx\PLS@driver\@empty
92 \def\PLS@temp{dvips}%
93 \ifnum 1=0\ifx\Gin@PS@raw\@undefined
94 \else
95 \ifx\Gin@PS@raw\relax
96 \else
97 \ifx\Gin@PS@raw\@empty
98 \else
99 1%
100 \fi
101 \fi
102 \fi
103 \space
104 \let\PLS@driver\PLS@temp
105 \PackageInfo{pdfscape}{%
106   Auto-detected driver: \PLS@temp\space(PostScript)%
107 }%
108 \fi
109 \fi

110 \ifx\PLS@driver\@empty
111 \PackageError{pdfscape}{%
112   Neither pdfTeX, PostScript, nor dvipdfm driver found%
113 } \@ehc
114 \fi

```

2.4 Driver implementation

- `\PLS@AddRotate #1`
it expects the correct rotation number in `#1` and implements the adding of the `/Rotation` entry in the `/Page` object of the current page.
- `\PLS@RemoveRotate`
it removes a previous `/Rotate` entry, if necessary.

2.4.1 pdfTeX

Not too nice is the global setting of `\pdfpageattr`. Perhaps this can be changed in future versions.

luatex compat.

```

115 \ifx\pdfpageattr\@undefined
116 \ifx\pdfvariable\@undefined\else
117   \protected\edef\pdfpageattr{\pdfvariable pageattr}
118 \fi
119 \fi

120 \def\PLS@temp{pdftex}
121 \ifx\PLS@temp\PLS@driver
122   \def\PLS@AddRotate#1{%
123     \ifnum#1=0 %

```

Already the default.

```

124   \else
125     \global\pdfpageattr\expandafter{%
126       \the\pdfpageattr
127       /Rotate #1%
128     }%
129   \fi
130 }%

```

Removes a `/Rotate` entry.

```

131 \def\PLS@RemoveRotate{%
132   \begingroup
133   \global\pdfpageattr\expandafter{\expandafter}%
134   \expandafter\PLS@@RemoveRotate
135   \the\pdfpageattr /Rotate\@nil
136 \endgroup
137 }%
138 \def\PLS@@RemoveRotate#1/Rotate#2\@nil{%

```

Append `/Rotate` free stuff to `\pdfpageattr`.

```

139 \global\pdfpageattr\expandafter{\the\pdfpageattr#1}%
140 \ifx\#2\%

```

Ready, because the detected `/Rotate` is part of the end marker: `/Rotate\@nil`

```

141 \else

```

First read in the argument of `/Rotate`, then continue parsing.

```

142   \afterassignment\PLS@@RemoveRotate
143   \count0=#2\@nil
144 \fi
145 }%
146 \fi

```

2.4.2 PostScript driver

```

147 \def\PLS@temp{dvips}
148 \ifx\PLS@temp\PLS@driver
149   \RequirePackage{atbegshi}%
150   \AtBeginShipout{\PLS@AtBeginShipout}%
151   \let\PLS@AtBeginShipout\@empty
152   \def\PLS@AddRotate#1{%
153     \ifnum#1=0 %
154   \else
155     \def\PLS@AtBeginShipout{%
156       \global\setbox\AtBeginShipoutBox\vbox{%
157         \Gin@PS@raw{%
158           [{ThisPage}]\string<\string</Rotate #1\string>\string>%
159         /PUT pdfmark%
160       }%

```

```

161      \box\AtBeginShipoutBox
162    }%
163  }%
164  \fi
165 }%
166 \def\PLS@RemoveRotate{\let\PLS@AtBeginShipout\@empty}%
167 \fi

```

2.4.3 Driver dvipdfm

```

168 \def\PLS@temp{dvipdfm}
169 \ifx\PLS@temp\PLS@driver
170   \RequirePackage{atbegshi}%
171   \AtBeginShipout{\PLS@AtBeginShipout}%
172   \let\PLS@AtBeginShipout\@empty
173   \def\PLS@AddRotate#1{%
174     \ifnum#1=0 %
175     \else
176       \def\PLS@AtBeginShipout{%
177         \global\setbox\AtBeginShipoutBox\vbox{%
178           \special{pdf: put @thispage <</Rotate #1>>}%
179           \box\AtBeginShipoutBox
180         }%
181       }%
182     \fi
183   }%
184   \def\PLS@RemoveRotate{\let\PLS@AtBeginShipout\@empty}%
185 \fi

```

2.5 Driver independent stuff

The landscape environment is extended by adding the correct `/Rotate` entries.

```

186 \g@addto@macro{\landscape}{\PLS@Rotate{90}}
187 \g@addto@macro{\endlandscape}{\PLS@Rotate{0}}

```

`\PLS@Rotate` Main macro, that sets the `/Rotate` entry.
Argument: any TeX number or nothing, that means zero.
Driver independent.

```

188 \def\PLS@Rotate#1{%
189   \begingroup
190   1. Check and validate the argument.
191   \PLS@CheckAngle{#1}%
192   \expandafter\endgroup
193   2. Remove previous \Rotate entry.
194   \expandafter\PLS@RemoveRotate
195   3. Add /Rotate entry.
196   \expandafter\PLS@AddRotate\expandafter{\the\count@}%
197 }

```

`\PLS@CheckAngle` Validates the rotation angle.
The result is stored in the count register `\count@`.
Driver independent.

```

195 \def\PLS@CheckAngle#1{%
196   Nothing means zero:
197   \ifx\\#1\\%
198     \count@=0 %
199   \else
200     \count@=#1\relax
201   \fi

```

Normalize to interval $-360 < \text{\count@} < 360$.

```
201 \@whilenum\count@>359\do{\advance\count@ -360 }%
202 \@whilenum\count@<-359\do{\advance\count@ 360 }%
```

Check values: 0, +/-90, +/-180, +/-270

```
203 \ifnum 1=0\ifnum\count@=0 \else
204     \ifnum\count@=90 \else
205     \ifnum\count@=-90 \else
206     \ifnum\count@=180 \else
207     \ifnum\count@=-180 \else
208     \ifnum\count@=270 \else
209     \ifnum\count@=-270 \else
210     1\fi\fi\fi\fi\fi\fi\relax
211 \PackageError{pdfscape}{%
212     Invalid value \the\count@\space for /Rotate%
213 }{\@ehc
214 \count@=0 %
215 \fi
216 }

217 \end{package}
```

3 Test

3.1 Driver detection tests

```
218 \test0
219 \NeedsTeXFormat{LaTeX2e}
220 \documentclass{minimal}
221 \usepackage{qstest}
222 \IncludeTests{*}
223 \LogTests{log}{*}{*}
224 \test0

225 \test1
226 \usepackage{ifpdf}
227 \ifpdf
228 \def\ExpectDriver{pdftex}%
229 \fi
230 \usepackage{ifxetex}%
231 \ifxetex
232 \def\ExpectDriver{dvipdfm}%
233 \fi
234 \usepackage{pdfscape}[2016/05/14]
235 \test1

236 \test2
237 \def\ExpectDriver{pdftex}
238 \usepackage{pdftex}{pdfscape}[2016/05/14]
239 \test2

240 \test3
241 \def\ExpectDriver{dvipdfm}
242 \usepackage{dvipdfmx}{pdfscape}[2016/05/14]
243 \test3

244 \test4
245 \def\ExpectDriver{dvips}
246 \usepackage{dvipsone}{graphics}
247 \usepackage{pdfscape}[2016/05/14]
248 \test4

249 \test0
250 \begin{document}
251 \begin{qstest}{driver}{driver}
```

```

252 \makeatletter
253 \Expect*{\PLS@driver}*{\ExpectDriver}%
254 \end{qstest}
255 \end{document}
256 \test0)

```

3.2 Test for \PLS@CheckAngle

```

257 (*test5)
258 \NeedsTeXFormat{LaTeX2e}
259 \documentclass{minimal}
260 \usepackage{qstest}
261 \IncludeTests{*}
262 \LogTests{log}{*}{*}
263 \usepackage{pdfscape}[2016/05/14]
264 \begin{document}
265 \begin{qstest}{checkangle}{checkangle}
266 \makeatletter
267 \def\Result{%
268   \def\ResultString{\the\count@}%
269 }%
270 \def\PackageError#1#2#3{%
271   \def\Result{%
272     \def\ResultString{error}%
273   }%
274 }%
275 \def\Test#1#2{%
276   \begingroup
277     \PLS@CheckAngle{#1}%
278     \Result
279     \Expect*{\ResultString}{#2}%
280   \endgroup
281 }%
282 \Test{0}{0}%
283 \Test{90}{90}%
284 \Test{180}{180}%
285 \Test{270}{270}%
286 \Test{360}{0}%
287 \Test{450}{90}%
288 \Test{540}{180}%
289 \Test{630}{270}%
290 \Test{720}{0}%
291 \Test{3600}{0}%
292 \Test{3690}{90}%
293 \Test{-90}{270}%
294 \Test{-180}{180}%
295 \Test{-270}{-90}%
296 \Test{-360}{0}%
297 \Test{-450}{270}%
298 \Test{540}{180}%
299 \Test{-630}{90}%
300 \Test{-720}{0}%
301 \Test{-3600}{0}%
302 \Test{-3690}{270}%
303 \Test{1}{error}%
304 \Test{-1}{error}%
305 \Test{123}{error}%
306 \end{qstest}
307 \end{document}
308 \test5)

```

3.3 Test for rotate

```

309 (*test6)

```



```

310 \NeedsTeXFormat{LaTeX2e}
311 \documentclass{article}
312 \usepackage{pdfscape}[2016/05/14]
313 \begin{document}
314 \section{Portrait page}
315 \begin{landscape}
316 \section{Landscape page}
317 Foo bar foo bar foo bar foo bar foo bar
318 foo bar foo bar foo bar foo bar foo bar.
319 \end{landscape}
320 \section{Portrait Section}
321 Foo bar
322 \begin{landscape}
323 \section{Again Landscape Section}
324 \newpage
325 \section{Second Page of Landscape Section}
326 \end{landscape}
327 \section{Second Last Portrait Page}
328 \newpage
329 \section{Last Portrait Page}
330 \end{document}
331 \end{test6}

332 (*result6)
333 /Page 1 /Rotate 0
334 /Page 2 /Rotate 90
335 /Page 3 /Rotate 0
336 /Page 4 /Rotate 90
337 /Page 5 /Rotate 90
338 /Page 6 /Rotate 0
339 /Page 7 /Rotate 0
340 \end{result6}

341 (*ExtractRotate)
342 /**
343  * ExtractRotate.java
344  *
345  * Copyright (C) 2007 by Heiko Oberdiek <heiko.oberdiek at gmail.com>
346  *
347  * Requires: PDFBox (http://www.pdfbox.org/)
348  *
349  * Syntax: java ExtractRotate <pdffile> <textfile>
350  *
351  * The <pdffile> is analyzed and for each page its rotation
352  * setting is printed in the <textfile>. Example:
353  * /Page 1 /Rotate 0
354  * /Page 2 /Rotate 90
355  */
356 import java.io.FileInputStream;
357 import java.io.FileWriter;
358 import org.pdfbox.pdfparser.PDFParser;
359 import org.pdfbox.pdmodel.PDDocument;
360 import org.pdfbox.pdmodel.PDDocumentCatalog;
361 import org.pdfbox.pdmodel.PDPage;
362
363 public class ExtractRotate {
364
365     public static void main(String[] args) {
366         try {
367             String infile = args[0];
368             String outfile = args[1];
369             FileWriter out = new FileWriter(outfile);
370             PDFParser parser =
371                 new PDFParser(new FileInputStream(infile));

```

```

372     parser.parse();
373     PDDocument document = parser.getPDDocument();
374     PDDocumentCatalog catalog = document.getDocumentCatalog();
375     int i = 0;
376     for (Object page: catalog.getAllPages()) {
377         i++;
378         out.write("/Page " + i + " " + "/Rotate "
379             + ((PDPage)page).findRotation() + "\n");
380     }
381     document.close();
382     out.close();
383 }
384 catch (Exception e) {
385     e.printStackTrace();
386     System.exit(1);
387 }
388 }
389 }
390 </ExtractRotate>

```

4 Installation

4.1 Download

Package. This package is available on CTAN¹:

[CTAN:macros/latex/contrib/oberdiek/pdflscape.dtx](#) The source file.

[CTAN:macros/latex/contrib/oberdiek/pdflscape.pdf](#) Documentation.

Bundle. All the packages of the bundle ‘oberdiek’ are also available in a TDS compliant ZIP archive. There the packages are already unpacked and the documentation files are generated. The files and directories obey the TDS standard.

[CTAN:install/macros/latex/contrib/oberdiek.tds.zip](#)

TDS refers to the standard “A Directory Structure for T_EX Files” ([CTAN:tds/tds.pdf](#)). Directories with `texmf` in their name are usually organized this way.

4.2 Bundle installation

Unpacking. Unpack the `oberdiek.tds.zip` in the TDS tree (also known as `texmf` tree) of your choice. Example (linux):

```
unzip oberdiek.tds.zip -d ~/texmf
```

Script installation. Check the directory `TDS:scripts/oberdiek/` for scripts that need further installation steps. Package `attachfile2` comes with the Perl script `pdfatfi.pl` that should be installed in such a way that it can be called as `pdfatfi`. Example (linux):

```
chmod +x scripts/oberdiek/pdfatfi.pl
cp scripts/oberdiek/pdfatfi.pl /usr/local/bin/
```

4.3 Package installation

Unpacking. The `.dtx` file is a self-extracting docstrip archive. The files are extracted by running the `.dtx` through plain T_EX:

```
tex pdflscape.dtx
```

¹<http://ctan.org/pkg/pdflscape>

TDS. Now the different files must be moved into the different directories in your installation TDS tree (also known as `texmf` tree):

```
pdfscape.sty      → tex/latex/oberdiek/pdfscape.sty
pdfscape.pdf      → doc/latex/oberdiek/pdfscape.pdf
test/pdfscape-test1.tex → doc/latex/oberdiek/test/pdfscape-test1.tex
test/pdfscape-test2.tex → doc/latex/oberdiek/test/pdfscape-test2.tex
test/pdfscape-test3.tex → doc/latex/oberdiek/test/pdfscape-test3.tex
test/pdfscape-test4.tex → doc/latex/oberdiek/test/pdfscape-test4.tex
test/pdfscape-test5.tex → doc/latex/oberdiek/test/pdfscape-test5.tex
test/pdfscape-test6.tex → doc/latex/oberdiek/test/pdfscape-test6.tex
test/pdfscape-test6.txt → doc/latex/oberdiek/test/pdfscape-test6.txt
test/ExtractRotate.java → doc/latex/oberdiek/test/ExtractRotate.java
pdfscape.dtx      → source/latex/oberdiek/pdfscape.dtx
```

If you have a `docstrip.cfg` that configures and enables `docstrip`'s TDS installing feature, then some files can already be in the right place, see the documentation of `docstrip`.

4.4 Refresh file name databases

If your $\text{T}_{\text{E}}\text{X}$ distribution (`teTEX`, `mikTEX`, ...) relies on file name databases, you must refresh these. For example, `teTEX` users run `texhash` or `mktextlsr`.

4.5 Some details for the interested

Unpacking with $\text{L}^{\text{A}}\text{T}_{\text{E}}\text{X}$. The `.dtx` chooses its action depending on the format:

plain $\text{T}_{\text{E}}\text{X}$: Run `docstrip` and extract the files.

$\text{L}^{\text{A}}\text{T}_{\text{E}}\text{X}$: Generate the documentation.

If you insist on using $\text{L}^{\text{A}}\text{T}_{\text{E}}\text{X}$ for `docstrip` (really, `docstrip` does not need $\text{L}^{\text{A}}\text{T}_{\text{E}}\text{X}$), then inform the autodetect routine about your intention:

```
latex \let\install=y\input{pdfscape.dtx}
```

Do not forget to quote the argument according to the demands of your shell.

Generating the documentation. You can use both the `.dtx` or the `.drv` to generate the documentation. The process can be configured by the configuration file `ltxdoc.cfg`. For instance, put this line into this file, if you want to have A4 as paper format:

```
\PassOptionsToClass{a4paper}{article}
```

An example follows how to generate the documentation with `pdfLATEX`:

```
pdflatex pdfscape.dtx
makeindex -s gind.ist pdfscape.idx
pdflatex pdfscape.dtx
makeindex -s gind.ist pdfscape.idx
pdflatex pdfscape.dtx
```

5 Catalogue

The following XML file can be used as source for the [T_EX Catalogue](#). The elements `caption` and `description` are imported from the original XML file from the Catalogue. The name of the XML file in the Catalogue is `pdfscape.xml`.

```
391 <(*catalogue>
392 <?xml version='1.0' encoding='us-ascii'?>
```

```

393 <!DOCTYPE entry SYSTEM 'catalogue.dtd'>
394 <entry datestamp='$Date$' modifier='$Author$' id='pdfscape'>
395   <name>pdfscape</name>
396   <caption>Make landscape pages display as landscape.</caption>
397   <authorref id='auth:oberdiek' />
398   <copyright owner='Heiko Oberdiek' year='2001,2004,2006-2008' />
399   <license type='lppl1.3' />
400   <version number='0.11' />
401   <description>
402     The package adds PDF support to the landscape environment of
403     package <xref refid='lscape'>lscape</xref>, by setting the PDF
404     <tt>/Rotate</tt> page attribute. Pages with this attribute will be
405     displayed in landscape orientation by conforming PDF viewers.
406   <p/>
407   The package is part of the <xref refid='oberdiek'>oberdiek</xref> bundle.
408 </description>
409 <documentation details='Package documentation'
410   href='ctan:/macros/latex/contrib/oberdiek/pdfscape.pdf' />
411 <ctan file='true' path='/macros/latex/contrib/oberdiek/pdfscape.dtx' />
412 <miktex location='oberdiek' />
413 <texlive location='oberdiek' />
414 <install path='/macros/latex/contrib/oberdiek/oberdiek.tds.zip' />
415 </entry>
416 </catalogue>

```

6 History

[2001/01/15 v0.1]

- First public version, published in [de.comp.text.tex](#):
“[Re: Querformat, pdfLaTeX und thumbpdf](#)”²

[2001/02/04 v0.2]

- Minor documentation update.
- CTAN.

[2004/05/11 v0.3]

- Support for dvipdfm added.

[2004/05/12 v0.4]

- Bug fix: support for multipage landscape environment for all drivers except for pdftex.

[2006/02/20 v0.5]

- DTX framework.
- LPPL 1.3
- Code is not changed.

[2006/04/24 v0.6]

- Bug fix: `\PLS@RemoveRotate` reinserted for `\PLS@Rotate`.
- Fix for `\PLS@RemoveRotate` (dvips/dvipdfm): `\PLS@EverhShi` hook is cleared.

²Url: <http://groups.google.com/group/de.comp.text.tex/msg/e054c5795e52d2b8>

[2007/04/11 v0.7]

- Line ends sanitized.

[2007/04/17 v0.8]

- Package atbegshi replaces everyshi.

[2007/10/21 v0.9]

- Driver detection for Xe_{La}TeX added.
- Fix for rotation angles ≤ -360 or ≥ 360 .

[2008/08/11 v0.10]

- Code is not changed.
- URLs updated.

[2016/05/14 v0.11]

- LuaTeX Compatibility

7 Index

Numbers written in *italic* refer to the page where the corresponding entry is described; numbers underlined refer to the code line of the definition; plain numbers refer to the code lines where the entry is used.

Symbols		E	
<code>\@ehc</code>	51, 69, 113, 213	<code>\end</code>	254, 255, 306, 307, 319, 326, 330
<code>\@empty</code>	5, 6, 21, 23, 30, 34, 42, 58, 74, 91, 97, 110, 151, 166, 172, 184	<code>\endlandscape</code>	187
<code>\@nil</code>	135, 138, 143	<code>\Expect</code>	253, 279
<code>\@undefined</code>	93, 115, 116	<code>\ExpectDriver</code>	228, 232, 237, 241, 245, 253
<code>\@whilenum</code>	201, 202	G	
<code>\@</code>	140, 196	<code>\g@addto@macro</code>	186, 187
A		<code>\Gin@driver</code>	78
<code>\advance</code>	201, 202	<code>\Gin@PS@raw</code>	93, 95, 97, 157
<code>\afterassignment</code>	142	I	
<code>\AtBeginShipout</code>	150, 171	<code>\ifnum</code>	93, 123, 153, 174, 203, 204, 205, 206, 207, 208, 209
<code>\AtBeginShipoutBox</code>	156, 161, 177, 179	<code>\ifpdf</code>	41, 227
B		<code>\ifx</code>	23, 30, 34, 42, 46, 58, 64, 74, 78, 91, 93, 95, 97, 110, 115, 116, 121, 140, 148, 169, 196
<code>\begin</code>	250, 251, 264, 265, 313, 315, 322	<code>\ifxetex</code>	57, 231
<code>\box</code>	161, 179	<code>\IncludeTests</code>	222, 261
C		L	
<code>\count</code>	143	<code>\landscape</code>	186
<code>\count@</code>	193, 197, 199, 201, 202, 203, 204, 205, 206, 207, 208, 209, 212, 214, 268	<code>\LogTests</code>	223, 262
<code>\CurrentOption</code>	9, 24, 26	M	
D		<code>\makeatletter</code>	252, 266
<code>\DeclareOption</code>	8, 22	<code>\MessageBreak</code>	49, 67
<code>\do</code>	201, 202	N	
<code>\documentclass</code>	220, 259, 311	<code>\n</code>	379
		<code>\NeedsTeXFormat</code>	2, 219, 258, 310

<code>\newpage</code>	324, 328	<code>\protected</code>	117
		<code>\ProvidesPackage</code>	3
P			
<code>\PackageError</code>	48, 66, 111, 211, 270	R	
<code>\PackageInfo</code>	44, 60, 80, 105	<code>\RequirePackage</code> . .	38, 39, 55, 149, 170
<code>\PassOptionsToPackage</code>	32, 36	<code>\Result</code>	267, 271, 278
<code>\pdfpageattr</code>		<code>\ResultString</code>	268, 272, 279
	115, 117, 125, 126, 133, 135, 139	S	
<code>\pdfvariable</code>	116, 117	<code>\section</code> 314, 316, 320, 323, 325, 327, 329	
<code>\PLS@@RemoveRotate</code> . .	134, 138, 142	<code>\setbox</code>	156, 177
<code>\PLS@AddRotate</code> . .	122, 152, 173, 193	<code>\space</code>	61, 81, 103, 106, 212
<code>\PLS@AtBeginShipout</code>	150,	<code>\special</code>	178
	151, 155, 166, 171, 172, 176, 184	T	
<code>\PLS@CheckAngle</code>	190, 195, 277	<code>\Test</code> . .	275, 282, 283, 284, 285, 286,
<code>\PLS@driver</code>	6, 10, 42,		287, 288, 289, 290, 291, 292,
	43, 46, 52, 58, 59, 64, 70, 74, 79,		293, 294, 295, 296, 297, 298,
	81, 91, 104, 110, 121, 148, 169, 253		299, 300, 301, 302, 303, 304, 305
<code>\PLS@option</code>	5, 9, 30, 32, 49, 67	<code>\the</code>	126, 135, 139, 193, 212, 268
<code>\PLS@RemoveRotate</code> 131, 166, 184, 192		U	
<code>\PLS@Rotate</code>	186, 187, 188	<code>\usepackage</code>	221, 226, 230, 234,
<code>\PLS@temp</code>	7, 13, 14,		238, 242, 246, 247, 260, 263, 312
	15, 16, 17, 18, 19, 20, 21, 23,	V	
	24, 26, 34, 36, 40, 43, 44, 46,	<code>\vbox</code>	156, 177
	52, 56, 59, 61, 64, 70, 73, 76,		
	78, 86, 87, 88, 89, 90, 92, 104,		
	106, 120, 121, 147, 148, 168, 169		
<code>\ProcessOptions</code>	29		